


Stimela startup guide

Start Stimela

First step: Change your current folder to the Stimela folder as can be seen in the figure below.



Second step: Type "*stimStartup*" in your Matlab command screen and hit Enter. Stimela will now start.


Import My_projects and My_models

First step: To import the My_projects and My_models from your old Stimela version copy them from your old My_Projects/Models folder to your new My_Projects/Models folder.

Second step: Next start Stimela.

Third step: Open My_projects and double click on the button "*Update My_projects to the latest Stimela version*". Stimela will now update your projects.

Fourth step: Repeat the previous step for My_models.



Common errors

Cannot find an exact (case-sensitive) match for 'function name'

The closest match is: "

This error can occur when you have switched to the new Stimela version.

Solution: Run the following command:

```
"stimUpdate('update', stimFolder('Stimela'), stimFolder('Main'))"
```

This function will try to replace all function calls with an inexact case match.